# Package: gofedf (via r-universe)

September 6, 2024

Title Goodness of Fit Tests Based on Empirical Distribution Functions

Version 1.0.0

Description Routines that allow the user to run goodness of fit tests based on empirical distribution functions for formal model evaluation in a general likelihood model. In addition, functions are provided to test a sample against Normal or Gamma distributions, validate the normality assumptions in a linear model, and examine the appropriateness of a Gamma distribution in generalized linear models with various link functions.

Michael Arthur Stephens (1976)

<http://www.jstor.org/stable/2958206>.

**License** GPL (>= 3)

URL https://github.com/pnickchi/gofedf

BugReports https://github.com/pnickchi/gofedf/issues

**Encoding** UTF-8

**Roxygen** list(markdown = TRUE)

RoxygenNote 7.3.1

**Depends** R (>= 2.10)

Imports stats, CompQuadForm, MASS, glm2, statmod

NeedsCompilation no

Author Richard Lockhart [aut], Payman Nickchi [aut, cre]

Maintainer Payman Nickchi <pnickchi@sfu.ca>

**Suggests** knitr, rmarkdown, testthat (>= 3.0.0)

Config/testthat/edition 3

VignetteBuilder knitr

Repository https://pnickchi.r-universe.dev

RemoteUrl https://github.com/pnickchi/gofedf

RemoteRef HEAD

**RemoteSha** 36de6ef14c8298cd5ee5e47b5a0548fd5a76374f

2 IGMLE

# **Contents**

IGMLE	:	Com Gaus								•	•		ne	te	rs	in	Ii	nv	ers	se
inuex																				14
Index																				14
	testYourModel		 																	11
	testNormal		 																	10
	testLMNormal		 																	8
	testGLMGamma		 																	6
	testGamma		 																	5
	testExponential		 																	4
	IGScore		 																	3
	IGPIT		 																	3
	IGMLE		 																	2

## Description

This function is used in testYourModel function for example purposes.

## Usage

```
IGMLE(obs, ...)
```

## **Arguments**

obs a numeric vector of sample observations.... a list of additional parameters to define the likelihood.

## Value

The function compute the MLE of parameters in Inverse Gaussian distribution and returns a vector of estimates. The first and second elements of the vector are MLE of the mean and shape, respectively.

IGPIT 3

IGPIT	Compute the probability integral transformed values for a sample from
10/ 11	Inverse Gaussian distribution.

## **Description**

This function is used in testYourModel function for example purposes.

## Usage

```
IGPIT(obs, ...)
```

#### **Arguments**

obs A numeric vector of sample observations.

... A list of additional parameters to define the likelihood.

## Value

A numeric vector of probability integral transformed values of sample observations.

IGScore Compute the score function of the Inverse Gaussian distribution based on a sample.

## **Description**

This function is used in testYourModel function for example purposes.

## Usage

```
IGScore(obs, ...)
```

## **Arguments**

obs a numeric vector of sample observations.... a list of additional parameters to define the likelihood.

## Value

The score matrix with n rows (number of sample observations) and 2 columns (mean and shape).

4 testExponential

testExponential

Apply Goodness of Fit Test for Exponential Distribution

#### **Description**

Performs the goodness-of-fit test based on empirical distribution function to check if an i.i.d sample follows an Exponential distribution.

## Usage

```
testExponential(
   x,
   discretize = FALSE,
   ngrid = length(x),
   gridpit = FALSE,
   hessian = FALSE,
   method = "cvm"
)
```

#### Arguments

X	a non-empty	numeric	vector	of sample d	ata.
^	a non empty	numence	VCCtOI	or sumple a	ata.

points (see ngrid and gridpit), and the integral equation is replaced by a matrix equation. If FALSE (the default value), the covariance function is first estimated, and then the integral equation is solved to find the eigenvalues. The results of our simulations recommend using the estimated covariance for solving the integral equation. The parameters ngrid, gridpit, and hessian are

only relevant when discretize = TRUE.

ngrid the number of equally spaced points to discretize the (0,1) interval for computing

the covariance function.

gridpit logical. If TRUE (the default value), the parameter ngrid is ignored and (0,1) in-

terval is divided based on probability integral transformed values obtained from the sample. If FALSE, the interval is divided into ngrid equally spaced points for

computing the covariance function.

hessian logical. If TRUE the Fisher information matrix is estimated by the observed Hes-

sian Matrix based on the sample. If FALSE (the default value) the Fisher infor-

mation matrix is estimated by the variance of the observed score matrix.

method a character string indicating which goodness-of-fit statistic is to be computed.

The default value is 'cvm' for the Cramer-von-Mises statistic. Other options include 'ad' for the Anderson-Darling statistic, and 'both' to compute both cvm

and ad.

.....

testGamma 5

#### Value

A list of two containing the following components:

- Statistic: the value of goodness-of-fit statistic.
- p-value: the approximate p-value for the goodness-of-fit test. if method = 'cvm' or method = 'ad', it returns a numeric value for the statistic and p-value. If method = 'both', it returns a numeric vector with two elements and one for each statistic.

#### **Examples**

```
set.seed(123)
n <- 50
sim_data <- rexp(n, rate = 2)
testExponential(x = sim_data)</pre>
```

testGamma

Apply Goodness of Fit Test for Gamma Distribution

## **Description**

Performs the goodness-of-fit test based on empirical distribution function to check if an i.i.d sample follows a Gamma distribution.

#### Usage

```
testGamma(
    x,
    discretize = FALSE,
    ngrid = length(x),
    gridpit = FALSE,
    hessian = FALSE,
    rate = TRUE,
    method = "cvm"
)
```

#### Arguments

discretize

ngrid

x a non-empty numeric vector of sample data.

If TRUE, the covariance function of W\_n(u) process is evaluated at some data points (see ngrid and gridpit), and the integral equation is replaced by a matrix equation. If FALSE (the default value), the covariance function is first estimated, and then the integral equation is solved to find the eigenvalues. The results of our simulations recommend using the estimated covariance for solving the integral equation. The parameters ngrid, gridpit, and hessian are

only relevant when discretize = TRUE.

the number of equally spaced points to discretize the (0,1) interval for computing

the covariance function.

6 testGLMGamma

gridpit	logical. If TRUE (the default value), the parameter ngrid is ignored and (0,1) interval is divided based on probability integral transformed values obtained from the sample. If FALSE, the interval is divided into ngrid equally spaced points for computing the covariance function.
hessian	logical. If TRUE the Fisher information matrix is estimated by the observed Hessian Matrix based on the sample. If FALSE (the default value) the Fisher information matrix is estimated by the variance of the observed score matrix.
rate	logical. If TRUE (the default value), the rate is estimated in Gamma distribution. If FALSE, scale is estimated. See GammaDist for more details.
method	a character string indicating which goodness-of-fit statistic is to be computed. The default value is 'cvm' for the Cramer-von-Mises statistic. Other options include 'ad' for the Anderson-Darling statistic, and 'both' to compute both cvm and ad.

#### Value

A list of two containing the following components:

- Statistic: the value of goodness-of-fit statistic.
- p-value: the approximate p-value for the goodness-of-fit test. if method = 'cvm' or method = 'ad', it returns a numeric value for the statistic and p-value. If method = 'both', it returns a numeric vector with two elements and one for each statistic.

#### **Examples**

```
set.seed(123)
sim_data <- rgamma(n = 50, shape = 3)
testGamma(x = sim_data)
sim_data <- runif(n = 50)
testGamma(x = sim_data)</pre>
```

testGLMGamma

Apply Goodness of Fit Test to the Residuals of a Generalized Linear Model with Gamma Link Function

## **Description**

testGLMGamma is used to check the validity of Gamma assumption for the response variable when fitting generalized linear model. Common link functions in glm can be used here.

## Usage

```
testGLMGamma(
    x,
    y,
    fit = NULL,
    1 = "log",
```

7 testGLMGamma

```
discretize = FALSE,
  ngrid = length(y),
  gridpit = TRUE,
 hessian = FALSE,
  start.value = NULL,
  control = NULL,
 method = "cvm"
)
```

#### **Arguments**

Х is either a numeric vector or a design matrix. In the design matrix, rows indicate observations and columns presents covariats.

is a vector of numeric values with the same number of observations or number У of rows as x.

> is an object of class glm and its default value is NULL. If a fit of class glm is provided, the arguments x, y, and 1 will be ignored. We recommend using glm2 function from glm2 package since it provides better convergence while optimizing the likelihood to estimate coefficients of the model by IWLS method. It is required to return design matrix by x = TRUE in glm or glm2 function. For more information on how to do this, refer to the help documentation for the glm or glm2 function.

a character vector indicating the link function that should be used for Gamma family. Acceptable link functions for Gamma family are inverse, identity and log. For more details see Gamma from stats package.

If TRUE, the covariance function of W\_n(u) process is evaluated at some data points (see ngrid and gridpit), and the integral equation is replaced by a matrix equation. If FALSE (the default value), the covariance function is first estimated, and then the integral equation is solved to find the eigenvalues. The results of our simulations recommend using the estimated covariance for solving the integral equation. The parameters ngrid, gridpit, and hessian are only relevant when discretize = TRUE.

the number of equally spaced points to discretize the (0,1) interval for computing the covariance function.

logical. If TRUE (the default value), the parameter ngrid is ignored and (0,1) interval is divided based on probability integral transformed values obtained from the sample. If FALSE, the interval is divided into ngrid equally spaced points for computing the covariance function.

logical. If TRUE the Fisher information matrix is estimated by the observed Hessian Matrix based on the sample. If FALSE (the default value) the Fisher information matrix is estimated by the variance of the observed score matrix.

a numeric value or vector. This is the same as start argument in glm or glm2. The value is a starting point in iteratively reweighted least squares (IRLS) algorithm for estimating the MLE of coefficients in the model.

a list of parameters to control the fitting process in glm or glm2 function. For more details, see glm. control.

fit

1

discretize

ngrid

gridpit

hessian

start.value

control

8 testLMNormal

method

a character string indicating which goodness-of-fit statistic is to be computed. The default value is 'cvm' for the Cramer-von-Mises statistic. Other options include 'ad' for the Anderson-Darling statistic, and 'both' to compute both cvm and ad.

#### Value

A list of two containing the following components:

- Statistic: the value of goodness-of-fit statistic.
- p-value: the approximate p-value for the goodness-of-fit test. if method = 'cvm' or method = 'ad', it returns a numeric value for the statistic and p-value. If method = 'both', it returns a numeric vector with two elements and one for each statistic.
- converged: logical to indicate if the IWLS algorithm have converged or not.

## **Examples**

```
set.seed(123)
n <- 50
p <- 5
x <- matrix( rnorm(n*p, mean = 10, sd = 0.1), nrow = n, ncol = p)
b <- runif(p)
e <- rgamma(n, shape = 3)
y <- exp(x %*% b) * e
testGLMGamma(x, y, l = 'log')
myfit <- glm(y ~ x, family = Gamma('log'), x = TRUE, y = TRUE)
testGLMGamma(fit = myfit)</pre>
```

testLMNormal

Apply Goodness of Fit Test to Residuals of a Linear Model

#### **Description**

testLMNormal is used to check the normality assumption of residuals in a linear model. This function can take the response variable and design matrix, fit a linear model, and apply the goodness-of-fit test. Conveniently, it can take an object of class "lm" and directly applies the goodness-of-fit test. The function returns a goodness-of-fit statistic along with an approximate p-value.

#### Usage

```
testLMNormal(
    x,
    y,
    fit = NULL,
    discretize = FALSE,
    ngrid = length(y),
    gridpit = TRUE,
    hessian = FALSE,
    method = "cvm"
)
```

testLMNormal 9

## **Arguments**

X	is either a numeric vector or a design matrix. In the design matrix, rows indicate observations and columns presents covariates.
у	is a vector of numeric values with the same number of observations or number of rows as $\mathbf{x}$ .
fit	an object of class "lm" returned by $lm$ function in stats package. The default value of fit is NULL. If any object is provided, x and y will be ignored and the class of object is checked. If you pass an object to fit make sure to return the design matrix by setting $x = TRUE$ and the response variable by setting in $y = TRUE$ in $lm$ function. To read more about this see the help documentation for $lm$ function or see the example below.
discretize	If TRUE, the covariance function of $W_n(u)$ process is evaluated at some data points (see ngrid and gridpit), and the integral equation is replaced by a matrix equation. If FALSE (the default value), the covariance function is first estimated, and then the integral equation is solved to find the eigenvalues. The results of our simulations recommend using the estimated covariance for solving the integral equation. The parameters ngrid, gridpit, and hessian are only relevant when discretize = TRUE.
ngrid	the number of equally spaced points to discretize the $(0,1)$ interval for computing the covariance function.
gridpit	logical. If TRUE (the default value), the parameter ngrid is ignored and (0,1) interval is divided based on probability integral transformed values obtained from the sample. If FALSE, the interval is divided into ngrid equally spaced points for computing the covariance function.
hessian	logical. If TRUE the Fisher information matrix is estimated by the observed Hessian Matrix based on the sample. If FALSE (the default value) the Fisher information matrix is estimated by the variance of the observed score matrix.
method	a character string indicating which goodness-of-fit statistic is to be computed. The default value is 'cvm' for the Cramer-von-Mises statistic. Other options include 'ad' for the Anderson-Darling statistic, and 'both' to compute both cvm and ad.

## Value

A list of two containing the following components:

- Statistic: the value of goodness-of-fit statistic.
- p-value: the approximate p-value for the goodness-of-fit test. if method = 'cvm' or method = 'ad', it returns a numeric value for the statistic and p-value. If method = 'both', it returns a numeric vector with two elements and one for each statistic.

## Examples

```
set.seed(123)
n <- 50
p <- 5
x <- matrix( runif(n*p), nrow = n, ncol = p)</pre>
```

10 testNormal

```
e <- rnorm(n)
b <- runif(p)
y <- x %*% b + e
testLMNormal(x, y)
# Or pass lm.fit object directly:
lm.fit <- lm(y ~ x, x = TRUE, y = TRUE)
testLMNormal(fit = lm.fit)</pre>
```

testNormal

Apply Goodness of Fit Test for Normal Distribution

#### Description

Performs the goodness-of-fit test based on empirical distribution function to check if an i.i.d sample follows a Normal distribution.

#### Usage

```
testNormal(
   x,
   discretize = FALSE,
   ngrid = length(x),
   gridpit = TRUE,
   hessian = FALSE,
   method = "cvm"
)
```

## Arguments

X	a non-empty nu	imeric vector	of sample data.

discretize If TRUE, the covariance function of  $W_n(u)$  process is evaluated at some data points (see ngrid and gridpit), and the integral equation is replaced by a ma-

trix equation. If FALSE (the default value), the covariance function is first estimated, and then the integral equation is solved to find the eigenvalues. The results of our simulations recommend using the estimated covariance for solving the integral equation. The parameters ngrid, gridpit, and hessian are

only relevant when discretize = TRUE.

ngrid the number of equally spaced points to discretize the (0,1) interval for computing

the covariance function.

gridpit logical. If TRUE (the default value), the parameter ngrid is ignored and (0,1) in-

terval is divided based on probability inverse transformed values obtained from the sample. If FALSE, the interval is divided into ngrid equally spaced points for

computing the covariance function.

hessian logical. If TRUE the Fisher information matrix is estimated by the observed Hes-

sian Matrix based on the sample. If FALSE (the default value) the Fisher information matrix is estimated by the variance of the observed score matrix.

testYourModel 11

method

a character string indicating which goodness-of-fit statistic is to be computed. The default value is 'cvm' for the Cramer-von-Mises statistic. Other options include 'ad' for the Anderson-Darling statistic, and 'both' to compute both cvm and ad.

#### Value

A list of two containing the following components:

- Statistic: the value of goodness-of-fit statistic.
- p-value: the approximate p-value for the goodness-of-fit test. if method = 'cvm' or method = 'ad', it returns a numeric value for the statistic and p-value. If method = 'both', it returns a numeric vector with two elements and one for each statistic.

#### **Examples**

```
set.seed(123)
sim_data <- rnorm(n = 50)
testNormal(x = sim_data)
sim_data <- rgamma(n = 50, shape = 3)
testNormal(x = sim_data)</pre>
```

testYourModel

Apply the Goodness of Fit Test Based on Empirical Distribution Function to Any Likelihood Model.

## **Description**

This function applies the goodness-of-fit test based on empirical distribution function. It requires certain inputs depending on whether the model involves parameter estimation or not. If the model is known and there is no parameter estimation, the function requires the probability transformed (or pit) values of the sample. This ought to be a numeric vector. If there is parameter estimation in the model, the function additionally requires the score as a matrix with n rows and p columns, where n is the sample size and p is the number of estimated parameters. The function checks if the sum of columns in score is near zero at the estimated parameter (which is assumed to be the maximum likelihood estimate).

#### Usage

```
testYourModel(
  pit,
  score = NULL,
  discretize = FALSE,
  ngrid = length(pit),
  gridpit = TRUE,
  precision = 1e-09,
  method = "cvm"
)
```

12 testYourModel

#### **Arguments**

pit The probability transformed (or pit) values of the sample which ought to be a numeric vector. score The default value is null and refers to no parameter estimation case. If there is parameter estimation, the score must be a matrix with n rows and p columns, where n is the sample size and p is the number of estimated parameters. If TRUE, the covariance function of W\_n(u) process is evaluated at some data discretize points (see ngrid and gridpit), and the integral equation is replaced by a matrix equation. If FALSE (the default value), the covariance function is first estimated, and then the integral equation is solved to find the eigenvalues. The results of our simulations recommend using the estimated covariance for solving the integral equation. The parameters ngrid, gridpit, and hessian are only relevant when discretize = TRUE. ngrid The number of equally spaced points to discretize the (0,1)interval for computing the covariance function. gridpit logical. If TRUE (the default value), the parameter ngrid is ignored and (0,1) interval is divided based on probability integral transformed values obtained from the sample. If FALSE, the interval is divided into ngrid equally spaced points for computing the covariance function. precision The theory behind goodness-of-fit test based on empirical distribution function (edf) works well if the MLE is indeed the root of derivative of log likelihood function. A precision of 1e-9 (default value) is used to check this. A warning message is generated if the score evaluated at MLE is not close enough to zero. method a character string indicating which goodness-of-fit statistic is to be computed. The default value is 'cvm' for the Cramer-von-Mises statistic. Other options

#### Value

A list of two containing the following components:

and ad.

- Statistic: the value of goodness-of-fit statistic.
- p-value: the approximate p-value for the goodness-of-fit test. if method = 'cvm' or method = 'ad', it returns a numeric value for the statistic and p-value. If method = 'both', it returns a numeric vector with two elements and one for each statistic.

include 'ad' for the Anderson-Darling statistic, and 'both' to compute both cvm

#### **Examples**

```
# Example: Inverse Gaussian (IG) distribution with weights
# Set the seed to reproduce example.
set.seed(123)
# Set the sample size
n <- 50</pre>
```

testYourModel 13

# **Index**

```
\mathsf{Gamma},\, \textcolor{red}{7}
{\tt GammaDist}, {\color{red} 6}
glm, 6, 7
glm.control, 7
glm2, 7
IGMLE, 2
IGPIT, 3
IGScore, 3
1m, 9
stats, 9
testExponential, 4
testGamma, 5
{\tt testGLMGamma}, {\color{red} 6}
testLMNormal, 8
testNormal, 10
testYourModel, 2, 3, 11
```